9/16/2019 GPIOPort

Digital package provides drivers for GPIO expanders.

GPIOPort

Summary

GPIOPort interface provides functions to use digital I/O.

Supported devices

- DS2408 (DS2408.html) (1-Wire)
- MCP230xx (MCP230xx.html) series (I2C): MCP23008, MCP23009, MCP23017, MCP23018
- MCP23Sxx (MCP23Sxx.html) series (SPI): MCP23S08, MCP23S09, MCP23S17, MCP23S18
- PCF8574 (PCF8574.html) (I2C)

Methods list

digitalCount()

Returns the digital channel count.

REST API: GET /devices/name/count

· name : device name from configuration file

digitalRead(channel)

Returns the value of the given digital channel.

REST API: GET /devices/name/channel/value

- · name (str): device name from configuration file
- channel (int): digital channel number

digitalReadAll()

Returns a list containing all digital channels value.

REST API : GET /devices/name/ * /value

• name (str): device name from configuration file

digitalWrite(channel, digit)

Write the value of the given digital channel.

REST API: POST /devices/name/channel/value/digit

- name (str): device name from configuration file
- channel (int): digital channel number
- digit (int): digital value (0 or 1)

9/16/2019 GPIOPort

portRead()

Returns an integer composed of all digital bits.

REST API: POST /devices/name/ * /integer

name (str): device name from configuration file

portWrite(value)

Write on all digital channels with an integer composed of all bits.

REST API : POST /devices/name/ * /integer/value

name (str): device name from configuration file

• value (int): integer value to write on the port.

getFunction(channel)

Returns the current fonction of the given digital channel.

· channel (int): digital channel number

REST API: Use getFunctionString instead.

getFunctionString(channel)

Returns the current fonction of the given digital channel.

REST API: GET /devices/name/channel/function

· name (str): device name from configuration file

· channel (int): digital channel number

setFunction(channel, func)

Setup the given digital channel with the given function

· channel (int): digital channel number

• func (int): GPIO.IN or GPIO.OUT

REST API: Use setFunctionString instead.

setFunctionString(channel, func)

Setup the given digital channel.

REST API: GET /devices/name/channel/function/func

name (str): device name from configuration file

• channel (int): digital channel number

• func (str): "IN" or "OUT"

wildcard()

Returns a list containing the current value and function of all digital channels.

9/16/2019 GPIOPort

REST API : GET /devices/name/ *

name (str): device name from configuration file

Python example

```
form webiopi.devices.digital import MCP23008
mcp = MCP23008(...)
                                # setup a MCP23008 I2C GPIO expander
# or
from webiopi import deviceInstance
mcp = deviceInstance("mcp")
                                # retrieve device named "mcp" in configuration file
mcp.getFunction(0)
                                # get current MCP digital channel 0 setup
mcp.setFunction(0, GPI0.OUT)
                                # setup MCP digital channel 0 as output
mcp.setFunction(1, GPI0.OUT)
                                # setup MCP digital channel 1 as output
mcp.setFunction(2, GPI0.OUT)
                                # setup MCP digital channel 2 as output
mcp.setFunction(3, GPIO.OUT)
                                # setup MCP digital channel 3 as output
mcp.digitalRead(4)
                                # read MCP digital channel 0
mcp.digitalWrite(4, GPIO.HIGH) # write MCP digital channel 4 as HIGH
mcp.portWrite(0x0F)
                                # write channels 0-3 as HIGH
mcp.portRead()
                                # read all MCP digital channels in a single integer
```

REST example

```
HTTP GET /devices/mcp/0/function # retrieve "mcp" channel 0 setup
HTTP GET /devices/mcp/0/value # retrieve "mcp" channel 0 digital value

HTTP POST /devices/mcp/0/function/out # set "mcp" channel 0 as output
HTTP POST /devices/mcp/0/value/1 # set "mcp" channel 0 as digital HIGH
```